

Settings

Home

Find a setting

System

Display

Notifications & actions

Power & sleep

Storage

Tablet mode

Multitasking

Projecting to this PC

Shared experiences

Remote Desktop

About

About

Your PC is monitored and protected.

✓ Virus & Threat Protection

✓ Firewall & Network Protection

✓ Device performance & Health

✓ App & Browser Control

[See details in Windows Defender](#)

Device specifications

Device name

Processor

Installed RAM

Device ID

Product ID

System type

Pen and touch

DESKTOP-29GLTRC

Intel(R) Core(TM) i7-3770 CPU @ 3.40GHz 3.40 GHz

16.0 GB (15.9 GB usable)

448DE9EB-7464-47BF-BA71-B8E4D1F63F32

00330-80000-00000-AA429

64-bit operating system, x64-based processor

No pen or touch input is available for this display

Rename this PC

Windows specifications

Edition

Version

OS Build

Windows 10 Pro

1709

16299.125

[Change product key or upgrade your edition of Windows](#)

[Read the Microsoft Services Agreement that applies to our services](#)

[Read the Microsoft Software License Terms](#)

Have a question?

[Get help](#)

Make Windows better

[Give us feedback](#)

Windows

Search

Task View

Edge

File Explorer

Store

Mail

Settings

ENG

9:52 AM

8/23/2022

- Settings
- General
 - System Information
 - Boot Sequence
 - Advanced Boot Options
 - Date/Time
 - System Configuration
 - Integrated NIC
 - Serial Port
 - SATA Operation
 - Drives
 - SMART Reporting
 - USB Configuration
 - Audio
 - Miscellaneous Devices
 - Video
 - Primary Display
 - Security
 - Admin Password**
 - System Password
 - Internal HDD-0 Password
 - Strong Password
 - Password Configuration
 - Password Bypass
 - Password Change
 - TPM Security
 - Computrace(R)
 - CPU XD Support
 - OROM Keyboard Access
 - Admin Setup Lockout
 - + Secure Boot
 - + Performance
 - + Power Management
 - + POST Behavior
 - + Virtualization Support
 - + Maintenance
 - + Image Server

Admin Password

Enter the old password:

Enter the new password:

Confirm new password:

OK

This field lets you set, change, or delete the administrator (admin) password (sometimes called the "setup" password). The admin password enables several security features. When set, it:

- * Restricts changes to the settings in Setup.
- * Restricts the boot devices listed in the F12 Boot Menu to those enabled in the "Boot Sequence" field.
- * Substitutes for the system password if the system prompts for a password during power on.

Successful changes to this password take effect immediately.

NOTE: If you delete the admin password, the system password, if set, is also deleted. Also, the admin password can be used to delete the HDD password. For this reason, you cannot set an admin password if a system password or HDD password is already set. The admin password must be set first if an admin password is used with a system password and/or HDD password.

Load Defaults

Apply

Exit

- Settings
 - General
 - System Information
 - Boot Sequence
 - Advanced Boot Options
 - Date/Time
 - System Configuration
 - Integrated NIC
 - Serial Port
 - SATA Operation
 - Drives
 - SMART Reporting
 - USB Configuration
 - Audio
 - Miscellaneous Devices
 - Video
 - Primary Display
 - Security
 - Admin Password
 - System Password**
 - Internal HDD-0 Password
 - Strong Password
 - Password Configuration
 - Password Bypass
 - Password Change
 - TPM Security
 - Computrace(R)
 - CPU XD Support
 - OROM Keyboard Access
 - Admin Setup Lockout
 - Secure Boot
 - Performance
 - Power Management
 - POST Behavior
 - Virtualization Support
 - Maintenance
 - Image Server

System Password

Enter the old password:

Enter the new password:

Confirm new password:

OK

This field lets you set, change, or delete the System password (previously called the "Primary" password). When this password is set, it

* Requires the password be entered when the system is powered on.

Successful changes to this password take effect immediately.

Load Defaults Apply Exit

Settings

- General
 - System Information
 - Boot Sequence
 - Advanced Boot Options
 - Date/Time
- System Configuration
 - Integrated NIC
 - Serial Port
 - SATA Operation
 - Drives
 - SMART Reporting
 - USB Configuration
 - Audio
 - Miscellaneous Devices
- Video
 - Primary Display
- Security
 - Admin Password
 - System Password
 - Internal HDD-0 Password**
 - Strong Password
 - Password Configuration
 - Password Bypass
 - Password Change
 - TPM Security
 - Computrace(R)
 - CPU XD Support
 - OROM Keyboard Access
 - Admin Setup Lockout
- Secure Boot
- Performance
- Power Management
- POST Behavior
- Virtualization Support
- Maintenance
- Image Server

Internal HDD-0 Password

Enter the old password: Enter the new password: Confirm new password:

OK

This option lets you set, change, or delete the password on the system's internal hard disk drive (HDD).

Successful changes to this password take effect immediately. Any change to this option will require a system reboot when you exit setup.

When an HDD password is set, it travels with the hard disk, so the disk is protected even if it is placed into another computer.

You must enter the password for a protected HDD whenever the drive is powered on. If you do not enter the correct password, the HDD will simply not function. It will remain in this state until you power the system off, power the system back on, and enter the correct password.

By default, the drive will not have a password set.

Load Defaults

Apply

Exit

DELL